# VID2MP4 Guide

Author: Kim Miikki Date: 15.9.2021

#### 1 Introduction

This program converts a video file (e.g., h264 format video file) to mp4 format. *Vid2mp4* is a frontend application for *MP4Box*. When the record speed in FPS is known and there is a PTS (Presentation Time Stamp) file present, the correct FPS value for the mp4 can be calculated. This is done in *vid2mp4.py* for accurate playback speed.

## 2 System Requirements

Operating System: ALL

Program: MP4Box (RPI/Ubuntu installation: sudo apt install -y gpac)

Python 3

## 3 Program Usage

Vid2mp4 has some arguments which are used for FPS adjustments and disabling generation of analysis plot files:

Only file is a mandatory argument for this program. Playback FPS is as default 25, but it can be overridden with a -fps argument. Correct video speed (slowdown, normal or speedup) can be controlled with the -rec argument and a PTS file. Generation of PTS graphs can be disabled with -n switch.

#### 4 Use Case

A short video was recorded with *fpsvideo.py* to demonstrate how to use this program. The video recorder created these files:

```
v-1440x768_100.0fps_10000ss_120s.pts
v-1440x768_100.0fps_10000ss_120s.h264
v-1440x768_100.0fps_10000ss_120s.rec
v-1440x768_100.0fps_10000ss_120s.mkv
v-1440x768_100.0fps_10000ss_120s.log
```


Originally the vide was captured in the h264 file, alongside with a pts file. These two files were required when converting to video to mp4 format with following command:

```
$ vid2mp4.py v-1440x768 100.0fps 10000ss 120s.h264 -rec 100
```

The stem for the pts file must be same as the stem for the video file. Otherwise the pts file is not read. Following files are created:

```
v-1440x768_100.0fps_10000ss_120s-histogram.png
v-1440x768_100.0fps_10000ss_120s-distribution.png
v-1440x768_100.0fps_10000ss_120s-intervals.txt
v-1440x768_100.0fps_10000ss_120s.mp4
v-1440x768_100.0fps_10000ss_120s-mp4.log
```

Interval distribution plots are generated and saved to two png files. The results are shown in Figure 1.






Figure 1. PTS file analyzed with graphs: interval distribution on left side, and probability and cumulative distribution function of the intervals on the right side.

The interval list is stored in a text file, where the stem is ended with "-intervals" string. A summary of selections and a statistical analysis can ar stored in the log file:

```
$ cat v-1440x768 100.0fps 10000ss 120s-mp4.log
vid2mp4.py log file
Log created on 2021.09.15-14:08:20
Program arguments:
FPS recorded: 100
FPS playback: 25
FPS: 16.434
Slowdown: 4.0x
Statistics:
Intervals: 7887
Frames
         : 7888
         : 15.21
Mean
Median
         : 19.91
Variance: 28.37
MP4 command:
```

MP4Box -add v-1440x768\_100.0fps\_10000ss\_120s.h264 -new v-

1440x768\_100.0fps\_10000ss\_120s.mp4 -fps 16.434

A MP4Box command is generated and executed in order to convert the original video file to a mp4 format file. This command is also stored in the log file, as shown above.

Individual frames can be extracted with *vid2pic.py*, as shown in Figure 2.




Figure 2. Frame 7830 extracted with vid2pic.py.

### The converted video file properties can be extracted and listed with *mediainfo*:

## $\label{eq:continuous_section} $$ $ mediainfo $ v-1440x768_100.0fps_10000ss_120s.mp4 $$ $$$

```
General
                                         : v-1440x768_100.0fps_10000ss_120s.mp4
Complete name
Format
                                         : MPEG-4
Format profile
                                        : Base Media
Codec ID
                                         : isom (isom/avc1)
File size
                                        : 153 MiB
Duration
                                        : 7 min 59 s
                                        : 2 672 kb/s
Overall bit rate
                                        : UTC 2021-09-15 11:08:11
Encoded date
                                        : UTC 2021-09-15 11:08:11
Tagged date
Video
                                        : 1
ID
Format
                                        : AVC
Format/Info
                                        : Advanced Video Codec
Format profile
                                        : <u>High@L4.2</u>
                                       : CABAC / 1 Ref Frames
Format settings
Format settings, CABAC
                                       : Yes
Format settings, ReFrames
                                        : 1 frame
Format settings, GOP
                                        M=1, N=60
Codec ID
                                        : avc1
Codec ID/Info
                                        : Advanced Video Coding
Duration
                                        : 7 min 59 s
                                        : 2 672 kb/s
Bit rate
                                        : 6 245 kb/s
Maximum bit rate
                                        : 1 440 pixels
Width
                                        : 768 pixels
Height
Display aspect ratio
                                        : 1.85:1
Frame rate mode
                                        : Constant
                                        : 16.434 FPS
Frame rate
Color space
                                        : YUV
                                        : 4:2:0
Chroma subsampling
Bit depth
                                        : 8 bits
Scan type
                                        : Progressive
                                        : 0.147
Bits/(Pixel*Frame)
Stream size
                                        : 153 MiB (100%)
Title
                                        : 0fps_10000ss_120s.h264@GPAC0.5.2-DEV-
revVersion: 0.5.2-426-gc5ad4e4+dfsg5-5
Encoded date
                                        : UTC 2021-09-15 11:08:11
Tagged date
                                        : UTC 2021-09-15 11:08:17
Codec configuration box
                                         : avcC
```