

# **Raspberry Pi High Speed Camera Software**

Kim Miikki and Alp Karakoç

## Table of Contents

1 List of Abbreviations and Symbols.....	3
2 Introduction.....	5
3 Prerequisites.....	5
3.1 Hardware.....	5
3.2 Operating System and Programs.....	6
3.3 Python and Required Libraries.....	8
3.4 Updating the software suite.....	10
3.5 RPI High Speed Camera Software.....	11
4 Launcher for RPI Camera Applications.....	14
5 Raspberry Pi Camera Module Information.....	15
6 Camera Preview for Composition.....	16
7 Video Preview with ROI for Composition.....	18
8 Region of Interest.....	20
8.1 Preview and Selection of a ROI.....	20
8.2 ROI Preview and Graphical Selection.....	21
8.3 Graphical ROI selection from a Single Picture.....	24
8.4 Camera Live Preview of a ROI area.....	25
8.5 Manual Selection of ROI.....	25
8.6 Crop Images in Batch by ROI.....	27
8.7 Sharpness Level Monitor and Camera.....	28
8.8 ROI Sharpness Level Monitor.....	30
8.9 Sharpness Live Graph Monitor.....	31
9 Auto Exposure Shutter Speed.....	32
10 Exposure Bracketing.....	32
11 Detect Minimum Exposure Time.....	36
12 Auto White Balance Gains.....	39
13 White Balance Calibration.....	39
13.1 Calibration procedure.....	41
13.2 Calibration with ROI.....	46
13.3 Analyze only mode.....	47
14 Get Optimum Gains from a Calibration File.....	47
15 Capturing Pictures in Manual Mode.....	48
15.1 Capturing Pictures with Preview Enabled.....	48
15.2 Camera with Preview.....	50
15.3 Capturing Pictures without Preview.....	53
16 Time-Lapse Photography.....	55
17 Video Recording.....	58
18 Creating Videos from Pictures.....	63
19 RGB Color Analysis.....	71
20 Splitting RGB Channels into Separate Images.....	74
20.1 Splitting RGB Channels into separate RGB Images.....	74
20.2 Splitting RGB Channels into Separate Gray Scale Images.....	76
21 Combining RGB split Images into Color Images.....	77
21.1 Combining 3 Channel RGB split Images into Color Images.....	77
21.2 Combining 1 Channel RGB split Images into Color Images.....	78
22 Batch Resize Images.....	78

Version – 26.10.2020

23 Convert Images to PNG Format.....	81
24 Pictures to Time-lapse Files.....	81
25 Additional Info.....	82

# 1 List of Abbreviations and Symbols

\$	Ordinary User in BASH Shell
$\mu$ s	microsecond = $10^{-6}$ s
ms	millisecond = $10^{-3}$ s
2K	2560x1400 resolution
720p	1280x720 resolution
A/R	Aspect Ratio
BW	Black and White (eg. Gray Scale)
CRF	Constant Rate Factor
CR2	Raw Image Format used by Canon Digital Cameras
CTRL	Control Key
FFmpeg	A complete, cross-platform solution to record, convert and stream audio and video
FHD	1980x1080, Full HD
FOV	Field Of View
FPS	Frames per Second
gparted	GNOME Partition Editor
H.264	Advanced Video Coding
HQ	High Quality (refers to the Raspberry Pi HQ camera module)
IR	Infrared
JPG	Lossy Compressed Image Format
Md	Raspberry Pi video mode
mkvmerge	Merge multimedia streams into a Matroska <sup>(tm)</sup> file
MKV	Matroska Multimedia Container (free and open-standard format)
MP	Mega Pixels
NoIR	No Infrared Filter
PIL	Python Imaging Library
PNG	Lossless Compressed Image Format
raspistill	Program for capturing still photographs with the camera module
raspivid	Program for capturing video with the camera module

Version – 26.10.2020

RGB Red, Green and Blue Color Channels

ROI Region of Interest

RPI Raspberry Pi

VGA 640x480 resolution

VIS Visible light

## 2 Introduction

Raspberry Pi combined with a camera module is a portable and cheap imaging system which. The camera (version 2.x) has an 8 MP sensor with a 1  $\mu$ s minimum exposure time. There are currently two different camera modules which the first is equipped with an IR filter and the second (NoIR) without it. Both modules provides 200 FPS high speed video recording at VGA resolution and 90 FPS at 720p resolution. A new HQ camera module has also been released on April of 2020. All of the camera applications has been updated to support the new camera module.

A camera module connected to a RPI can be used in many different ways. This is due to the programmability of the system. There are four applications (`raspistill`, `raspivid`, `raspiyuv` and `raspividyuv`) which can be used without programming new applications. Unfortunately they have a lot of options and therefore with script generation software it is possible to make their use much easier. Some of the Python application described in this manual work in this way. An other way is to use RPI camera libraries and create applications with their functions.

All of these programs (Python scripts) are licensed under MIT license.

## 3 Prerequisites

### 3.1 Hardware

All programs have been tested to work with the following hardware:

Raspberry Pi 4 Model B 4 GB

Raspberry Pi CMOS CAMERA MODULE NoIR V2 8MPx or Raspberry Pi CMOS CAMERA MODULE V2 8MPx

Raspberry Pi HQ Camera 12.3 MP camera module

16 GB Raspberry Pi NOOBS (New Out of Box Software)

USB 3 SSD drive for storage of images or videos

Flicker free light source(s) if exposure time is under 10-20 ms

Some of the programs have been developed with a Raspberry Pi 3 Model B, but the newest versions of the applications have not been tested to work in that environment.

## 3.2 Operating System and Programs

The system is developed and tested to work with *Raspbian GNU/Linux 10 (buster)*. Following steps (software installation etc.) have to be done in order to run applications which are described in this manual:

### Configure a SSD Drive

```
$ lsblk → /sda
```

*Start gparted*

Remove all partitions from the SSD drive

Device → create partition table

msdos <Apply>

Partition > New

File system: ext4

Label: ssd

```
$ sudo tune2fs -m 0 /dev/sda1
```

### Create /opt/tools directory and add it into the PATH variable

```
$ sudo mkdir /opt/tools
```

*Copy RPI camera applications to /opt/tools directory*

```
$ sudo chmod ugo+rx *.py
```

```
$ sudo nano /etc/profile.d/tools.sh  
export PATH="$PATH:/opt/tools"
```

```
$ reboot
```

### Create desktop shortcuts

campreview.py

vidpreview.py

Documents -> /opt/tools/documentation

### Raspberry Pi Configuration (Preferences > RPC)

System > Auto login: [v] Login as user 'Pi'

Interfaces

Camera	(*) Enable
SSH	(*) Enable
SPI	(*) Enable
I2C	(*) Enable

Performance

GPU Memory: 76 → 512

```
$ reboot
```

Version – 26.10.2020

**Run the next command in order to test that camera module is working normally:**

```
$ raspistill -t 0
```

*This will show camera live preview forever (exit by CTRL+C).*

**More comprehensive test can be done with the following command:**

```
$ raspistill -v -o test.png
```

### **Update RPI Firmware**

```
$ sudo apt rpi-update
```

```
$ reboot
```

### **Additional programs**

```
$ sudo apt install mkvtoolnix* exif exifprobe exiftags xscreensaver gparted gnome-disk-utility  
libraw-dev xclip xsel mediainfo ipython3 filezilla gnome-screenshot dos2unix
```

### **Prerequisites for gtlvideo.py**

```
$ sudo apt install libraw-dev
```

```
$ sudo apt install ffmpeg
```

### **Gimp**

```
$ sudo apt install gimp gimp-plugin* gimp-data-extras gimp-lensfun gimp-g* gimp-help-common  
gimp-help-en gimp-resynthesizer gimp-texturize
```

### **Development libraries for opencv-python**

```
sudo apt install libgtk2.0-dev pkg-config
```

### 3.3 Python and Required Libraries

In order to run RPI camera applications Python version must be at least 3.5. The version is checked at least by gtlvideo.py.

These steps are required to be done before running the RPI camera applications:

```
sudo pip3 install --upgrade pip
sudo pip3 install path.py
sudo pip3 install rawpy
sudo pip3 install Pillow
sudo pip3 install imageio
sudo pip3 install exifread
sudo pip3 install numpy pandas
sudo pip3 install pyperclip
sudo pip3 install dlib face_recognition imutils
sudo pip3 install pysimplegui
sudo pip3 install Cython
sudo pip3 install scikit-build
```

In addition, the following applications must be installed:

```
sudo apt install opencv*
sudo apt install libatlas-base-dev
sudo apt install libjasper-dev
sudo apt install libqtgui4
sudo apt install python3-pyqt5
sudo apt install libqt4-test
sudo apt install python3-opencv
sudo apt install build-essential cmake pkg-config
sudo apt install libatlas3-base libgfortran5
```

Version – 26.10.2020

```
$ sudo pip3 install numpy==1.19.1 --extra-index-url https://www.piwheels.org/simple
$ sudo pip3 install matplotlib==3.3.1 --extra-index-url https://www.piwheels.org/simple
$ sudo pip3 install --no-binary :all: opencv-python
Looking in indexes: https://pypi.org/simple, https://www.piwheels.org/simple
Collecting opencv-python
  Using cached opencv-python-4.4.0.42.tar.gz (88.9 MB)
  Installing build dependencies ... done
  Getting requirements to build wheel ... done
    Preparing wheel metadata ... done
Requirement already satisfied: numpy>=1.14.5 in /usr/local/lib/python3.7/dist-packages (from opencv-python) (1.19.1)
Building wheels for collected packages: opencv-python
  Building wheel for opencv-python (PEP 517) ... done
    Created wheel for opencv-python: filename=opencv_python-4.4.0.42-cp37-cp37m-linux_armv7l.whl size=10294672
sha256=1af48e51176c1ae154d2939686ec27f04e14f7fe53381541c46f82d576fd5eff
  Stored in directory:
/root/.cache/pip/wheels/87/89/42/0452b33622ef8f0fd9b90a8f199a7ab909e914e1432ea17b06
Successfully built opencv-python
Installing collected packages: opencv-python
Successfully installed opencv-python-4.4.0.42
Build time ~2 h
```

```
sudo pip3 install scipy
Looking in indexes: https://pypi.org/simple, https://www.piwheels.org/simple
Collecting scipy
  Using cached scipy-1.5.2.tar.gz (25.4 MB)
  Installing build dependencies ... done
  Getting requirements to build wheel ... done
    Preparing wheel metadata ... done
Building wheels for collected packages: scipy
  Building wheel for scipy (PEP 517) ... done
    Created wheel for scipy: filename=scipy-1.5.2-cp37-cp37m-linux_armv7l.whl size=50722066
sha256=58285d415bd0469e304a76154822db4eae20a0a58463a1241bda8c5204a6b68c
  Stored in directory:
/root/.cache/pip/wheels/3c/79/d0/bc51e2a8870685fb1ae515c967d15b7a89dfd530a99717f1fc
Successfully built scipy
Installing collected packages: scipy
Successfully installed scipy-1.5.2
Build time <1 h
```

Version – 26.10.2020

### **Pyhton IDE**

```
$ sudo apt install spyder3
```

### **Changing pyhton on pip versions by using alias**

```
$ nano .bash_aliases
```

```
alias python=python3
```

```
alias pip=pip3
```

```
$ reboot
```

## **3.4 Updating the software suite**

Latest version of the RPI software soite can be found here:

<https://github.com/kmiikki/rpi-camera>

The software and documentation can be downloaded as a ZIP package by pressing <Code> button and Selecting ‘Download ZIP’. It should be unpacked to a desired directory. To install or update the software on a RPI following command should be executed:

```
$ bash deploy-tools.sh
```

The script will create necessary sub-directories under /opt:

/opt/tools	programs
/opt/tools/rpi	common functions for RPI software suite programs
/opt/tools/documentation	documentation

Program directory should be included in PATH environment variable. Current path can be printed from terminal:

```
$ printenv PATH
```

Persistent path can be done by creating a script under /etc/profile.d/:

```
$ sudo nano /etc/profile.d/tools.sh
export PATH="$PATH:/opt/tools"
```

## 3.5 RPI High Speed Camera Software

The RPI High Speed Camera Software will be available from GitHUB in the summer of 2020. Meanwhile they are only available from the author in Aalto University. Until they are released, the applications may only be used at Aalto University.

Some of these applications can be executed on any operating system if Python 3.5 is installed. Also some open source programs must be present, especially if Python application generates scripts for these programs.

### List of RPI camera module applications

#### awb\_gains.py

- Get auto white balance gains for red and blue channels

#### bracket-exposure.py

- Determine an optimal exposure time by capturing images with different exposures

#### bw-rgbsplit

- Split RGB channels of pictures into separate images (1 channel gray scale)

#### bw-rgbcombine

- Combine one channel R, G, B pictures into RGB pictures

#### calibratecam.py

- Calibrate camera module white balance red and blue gains

#### camapps.py

- High speed camera software suite application launcher

#### camera.py

- Camera which captures JPG images

#### camera\_model.py

- Get camera information

#### campreview.py

- Camera preview for composition

#### capturepics.py

- Capture pictures manually without preview

#### capturepics-preview.py

- Capture lossless pictures manually with preview

Version – 26.10.2020

[capture-sharpness.py](#)

- Sharpness level monitor and camera

[dminexp.py](#)

- Detect minimum exposure time

[expss.py](#)

- Get auto exposure shutter speed

[fpsvideo.py](#)

- Record videos in slow, normal or high speed

[gen\\_tlfiles.py](#)

- Copy and rename pictures to time-lapse files

[gtlvideo.py](#)

- Generate videos from pictures

[optimum\\_gains.py](#)

- Get optimal red and blue gains from a Calibration File

[pics2png.py](#)

- Convert image formats which PIL supports to png format

[resize-batch.py](#)

- Batch resize images

[rgbinfo.py](#)

- Calculate RGB and BW means of pictures

[rgbsplit.py](#)

- Split RGB channels of pictures into separate images (3 color channels)

[rgbcombine.py](#)

- Combine R, G, B channel pictures into RGB pictures

Version – 26.10.2020

roiapps.py

- High speed camera ROI software suite application launcher

roi-batch.py

- ROI batch crop images

roi-manual.py

- Selection of ROI by values

roi-picture.py

- ROI graphical selection from a single picture

roi-preview.py

- Camera live ROI preview

roi-select.py

- ROI preview and graphical selection

roi-sharpness.py

- ROI focusing tool with sharpness monitor

sharpmon.py

- Sharpness live graph client for capture-sharpness.py

timelapse.py

- Capture time-lapse pictures

vidpreview.py

- Video preview with ROI for composition

## 4 Launcher for RPI Camera Applications

camapps.py

- High speed camera software suite application launcher
- RPI is not required

Most of applications which are described in this manual, can be launched from this program. Different tasks are organized under following categories: Composition, Exposure, White Balance Calibration, Images and Videos, Image Analysis and Operations. Their tasks are listed in the following example:

```
$ camapps.py
RPI High Speed Camera Software Suite (C) Kim Miikki 2020

Composition
 1 Camera info
 2 Camera preview
 3 Video preview

Exposure
 4 Auto exposure shutter speed
 5 Exposure bracketing
 6 Detect minimum exposure time

White Balance Calibration
 7 Auto white balance (AWB) gains
 8 Optimal gains from a calibration file
 9 Calibration

Images and Videos
10 Camera
11 Camera without preview
12 Time-lapse
13 Video recorder

Image Analysis and Operations
14 Create videos from images
15 Color analysis
16 Split images to RGB channels
17 Combine RGB channels to color images
18 Split RGB channels to gray scale
19 Combine RGB gray scale channels to color images
20 Convert images to PNG format
21 Images to time-lapse files
 0 Exit

Select task (0...21, Default=0: <Enter>):
```

## 5 Raspberry Pi Camera Module Information

camera\_model.py

- Get Raspberry Pi camera module information
- RPI camera module is required

This application gives information about attached camera module: sensor model, megapixels and camera resolution. Here is an example of the HQ camera module:

```
$ camera_model.py
Raspberry Pi camera module
revision:      imx477
model:        RP_imx477
make:         RaspberryPi
megapixels:   12.3
max x:        4056
max y:        3040
```

## 6 Camera Preview for Composition


camerapreview.py

- Camera Preview for Composition
- Requires a RPI and a camera module
- Uses PiCamera library

The first step in order to capture pictures or videos is to preview the composition. An application designed for this task is named **campreview.py**. Although same task can be done with the following command: raspistill -t 0, campreview.py does little more. From the current screen resolution it determines if there are two preview choices. Those are demonstrated by the following two pictures:



*Full preview composition with margins.*



*Full screen and cropped preview composition without margins.*

One can find in the source code following variables: maxx\_tested and maxy\_tested. They describe maximum preview window resolution which gives in full screen preview mode full composition. Beyond these values full screen preview will give a cropped composition. Unfortunately the values are not the same for every resolution. In the code the maximum tested preview size 1615x1200. So full composition in full screen will be always available for the resolution of 1280x1024 (which is available on RPI 4 Model B). FHD resolution will give margins if full composition is desired.

Caution! The application must be executed in terminal. Otherwise it is very difficult to exit the program.

Here is an example how to run the application in FHD mode:

```
Raspberry Pi camera module live preview  
Full screen and cropped preview (Y/N, default: N <ENTER>)  
Default selected  
Preview:      ENTER  
Exit program: ESC
```

Preview will start by pressing Enter and end by pressing ESC.

## 7 Video Preview with ROI for Composition

vidpreview.py

- Video Preview for Composition
- Requires a RPI and a camera module
- Calculates ROIs for all supported video modes
- Uses PiCamera library

RPI camera module (ver. 2.x) have a set of video modes that can be used when recording videos. The following table summarizes which modes are available, their resolutions, regions of interests etc:

Md	Video mode	A/R	FPS	FOV	Binning	Sensor area	ROI X0	ROI Y0	ROI W	ROI H
1	1920x1080	16:9	30	Partial	None	1920x1080	680	692	1920	1080
2	1920x1080	16:9	15	Full	None	3280x1845	0	310	3280	1845
3	1920x1080	16:9	15	Full	None	3280x1845	0	310	3280	1845
4	1640x1232	4:3	40	Full	2x2	3280x2464	0	0	3280	2464
5	1640x922	16:9	40	Full	2x2	3280x1845	0	310	3280	1845
6	1280x720	16:9	90	Partial	2x2	2560x1440	360	512	2560	1440
7	640x480	4:3	200	Partial	2x2	1280x960	1000	752	1280	960

*RPI camera module 2.x video modes*

The table of video modes shows that the only mode, which gives full field of view (= maximum sensor area), is mode number 4. Modes 2-5 gives full FOV, but in modes 2, 3 and 6 not whole sensor area is used for capturing videos. This is due to different A/R from the sensor to video resolution. Mode 1 captures videos in FHD mode and modes 6 and 7 are high speed recording modes (up to 90 or 200 FPS). Binned 2x2 modes have better sensitivity than non binned mode, because the sensor data per pixel is collected from a 2x2 square of sensor pixels.

This application only asks for a desired video mode (1-8). Normalized ROI values (0...1) are calculated and a live preview of the selected video mode is enabled, until ESC is pressed.

The HQ camera has fewer video modes which are shown in the following table. All of the documented resolutions [1] did not work on 3.6.2020. Hence a manual testing was required in order to get working video resolutions.

Md	Video mode	A/R	FPS	FOV	Binning
1	2028x1080	16:9	50	Partial	2x2
2	2028x1080	16:9	50	Full	2x2
3	1600x1200	16:9	10	Full	None
4	1012x760	4:3	120	Full	4x4

*RPI HQ camera module manually tested video modes*

Version – 26.10.2020

Here is an example how to run this application:

```
$ vidpreview.py
Raspberry Pi camera v. 2.x video preview

Video modes
Md Video      A/R   W     H      ROI W   ROI H
1  1920x1080 16:9 1920 1080  1920 1080
2  1920x1080 16:9 1920 1080  3280 1845
3  1920x1080 16:9 1920 1080  3280 1845
4  1640x1232 4:3  1640 1232  3280 2464
5  1640x922 16:9 1640  922  3280 1845
6  1280x720 16:9 1280  720  2560 1440
7  640x480  4:3  640   480  1280  960

Preview:      Md
Exit program: ESC
```

**Key 6 pressed**

```
Md:    6
ROI: 0.109756,0.207792,0.780488,0.584416
```

**ESC key terminates the video preview and the program**

Cited references:

[1] <https://www.raspberrypi.org/documentation/raspbian/applications/camera.md>, 3.6.2020

## 8 Region of Interest

Often only a part of an image is desired. This area is called ROI (Region of Interest). Raspistill and raspivid accepts a -roi parameter, followed by a starting point of ROI, its width and height. These values are normalized from 0 to 1. For an example, the ROI parameter for FOV is -roi 0,0,1,1.

Most of the the RPI software suite ROI applications are collected under a software launcher: roiapps.py. Selection of ROI generates a roi.ini file which is used in several applications. The ini file contains information about image size, crop coordinates and normalized crop values. It should be placed in the working directory before launching a ROI application.

### 8.1 Preview and Selection of a ROI

roiapps.py

- High speed camera ROI software suite application launcher
- RPI is not required

This software launcher has two categories: ROI and focusing tools. In the first category ROI can be selected from a live preview picture, saved picture or by entering values. Thereafter ROI can be used in camera live preview, batch cropping and with ROI sharpness level monitor. Selection of a task is done from following menu:

```
$ roiapps.py
RPI High Speed Camera ROI Software Suite (C) Kim Miikki and Alp
Karakoc 2020
```

Region of Interest

- 1 Preview and selection
- 2 ROI from a single picture
- 3 ROI camera preview
- 4 ROI manual selection
- 5 Batch crop

Focusing Tools

- 6 ROI sharpness level monitor
  - 7 Sharpness level monitor and camera (server)
  - 8 Sharpness live graph monitor (client)
- 0 Exit

Select task (0...8, Default=0: <Enter>):

## 8.2 ROI Preview and Graphical Selection

roi-select.py

- ROI preview and graphical selection
- Requires opencv Python library
- RPI and a camera module are required

This application has a straightforward workflow: compose the image, capture and save the image, open it automatically, select ROI graphically and generate roi.ini into current working directory. In addition of this, a ROI cropped image will be saved. This workflow is demonstrated here:

```
$ roi-select.py
Raspberry Pi Camera ROI Preview and Selection
Capture image mode (Y/N, Default y: <Enter>):
Default selected: Capture initial picture from camera enabled
Current directory:
/media/pi/data/20201019-LaserLiner_to_manual
Capture initial frame: SPACE
Exit program: ESC
```



*Composition of the image. Initial frame is captured by pressing SPACE.*

Version – 26.10.2020

Capturing initial frame...

Select a ROI and then press SPACE or ENTER button!

Cancel the selection process by pressing c button!



*Initial frame opened with OpenCV. The ROI is selected graphically and the selection is approved by pressing ENTER or SPACE.*

Roi option: -roi 0.3333,0.3326,0.2638,0.1859

The program generate following files to current directory:

roi-fov.png

roi-image.png

roi.ini

The first file is the initial frame, second is ROI cropped image if the initial frame and third file contains image and ROI information.

Version – 26.10.2020



*Initial frame with full field of view: roi-fov.png*



*Cropped image by region of interest: roi-image.png*

Version – 26.10.2020

Contents of roi.ini:

```
scale;coordinate name;value
original;img_x0;0
original;img_x1;4056
original;img_y0;0
original;img_y1;3040
original;crop_x0;1352
original;crop_x1;2422
original;crop_y0;1011
original;crop_y1;1576
normalized;roi_x0;0.3333
normalized;roi_y0;0.3326
normalized;roi_w;0.2638
normalized;roi_h;0.1859
```

These pictures were captured with a HQ camera, 16 mm tele lens and 2 stacked +4 dpt close-up lenses.

## 8.3 Graphical ROI selection from a Single Picture

### roi-picture.py

- ROI selection from a single picture
- Requires opencv and PySimpleGui Python libraries

This application is quite similar to roi-select.py but instead of capturing images a existing image is opened. Name or path of the image is asked with the following dialog:



Thereafter the workflow is similar to roi-select.py

## 8.4 Camera Live Preview of a ROI area

roi-preview.py

- Camera live ROI preview
- RPI, camera module and roi.ini are required

Selected ROI area can be previewed live with roi-preview.py. Pressing space toggles between ROI and FOV of the composition:

```
$ roi-preview.py
Raspberry Pi Camera ROI Preview
Toggle between FOV and ROI: SPACE
Exit program: ESC
```



*Toggle between ROI and FOV preview.*

## 8.5 Manual Selection of ROI

roi-manual.py

- Selection of ROI by values
- Requires opencv Python library

In order to create roi.ini with specific coordinates or with predefined width and height, roi-manual.py could be used. Picture size is read from an image file, if it is given as an argument to the python script. Absolute mode for coordinates can be selected by changing the value of absolut\_mode to True instead of False. This has to be done by editing the source file. Following example shows how to use this tool:

```
$ roi-manual.py ptfh2o-frame00000001.jpg
```

ROI manual selection


Current directory:  
/media/pi/data/PTFE

Version – 26.10.2020


```
Region of Interest
-----
Select X0 (0...4055, Default=0: <Enter>) : 1468
Select Y0 (0...3039, Default=0: <Enter>) : 1632
Select Width (1...2588, Default=2588: <Enter>) : 1280
Select Height (1...1408, Default=1408: <Enter>) : 1024

Roi option: -roi 0.3619,0.5368,0.3156,0.3368
pi@rpicam:/media/pi/data/PTFE $ ls
ptfe-h2o-frame00000001.jpg  ptfe-h2o-frame00000300.jpg  roi.ini
ptfe-h2o-frame00000100.jpg  ptfe-h2o-frame00000400.jpg
ptfe-h2o-frame00000200.jpg  ptfe-h2o-frame00000500.jpg
pi@rpicam:/media/pi/data/PTFE $ cat roi.ini
scale;coordinate name;value
original;img_x0;0
original;img_x1;4056
original;img_y0;0
original;img_y1;3040
original;crop_x0;1468
original;crop_x1;2748
original;crop_y0;1632
original;crop_y1;2656
normalized;roi_x0;0.3619
normalized;roi_y0;0.5368
normalized;roi_w;0.3156
normalized;roi_h;0.3368
```

The difference of FOV and ROI images can bee seen in these pictures:



FOV: 4056x3040



ROI: 1280x1024

## 8.6 Crop Images in Batch by ROI

roi-batch.py

- ROI batch crop images
- Requires opencv Python library

A very convenient method to crop images in batch is to use roi-batch.py. This program should be executed in the working directory where images to be cropped are located. Their dimensions must be same as the dimensions defined in roi.ini. Here is an illustrative example how to use this tool:

```
$ roi-batch.py
ROI batch crop tool
ptfe-h2o-frame00000001.jpg (4056x3040) : -> ptfe-h2o-frame00000001.jpg
ptfe-h2o-frame00000100.jpg (4056x3040) : -> ptfe-h2o-frame00000100.jpg
ptfe-h2o-frame00000200.jpg (4056x3040) : -> ptfe-h2o-frame00000200.jpg
ptfe-h2o-frame00000300.jpg (4056x3040) : -> ptfe-h2o-frame00000300.jpg
ptfe-h2o-frame00000400.jpg (4056x3040) : -> ptfe-h2o-frame00000400.jpg
ptfe-h2o-frame00000500.jpg (4056x3040) : -> ptfe-h2o-frame00000500.jpg

Pictures converted: 6
Time elapsed:      0:00:04.937757
pi@rpicam:/media/pi/data/PTFE $ tree
.
├── ptfe-h2o-frame00000001.jpg
├── ptfe-h2o-frame00000100.jpg
├── ptfe-h2o-frame00000200.jpg
├── ptfe-h2o-frame00000300.jpg
├── ptfe-h2o-frame00000400.jpg
└── ptfe-h2o-frame00000500.jpg
├── roi
│   ├── ptfe-h2o-frame00000001.jpg
│   ├── ptfe-h2o-frame00000100.jpg
│   ├── ptfe-h2o-frame00000200.jpg
│   ├── ptfe-h2o-frame00000300.jpg
│   ├── ptfe-h2o-frame00000400.jpg
│   └── ptfe-h2o-frame00000500.jpg
└── roi.ini

1 directory, 13 files
pi@rpicam:/media/pi/data/PTFE/roi $ mediainfo roi/ptfe-h2o-frame00000001.jpg
General
Complete name          : ptfe-h2o-frame00000001.jpg
Format                 : JPEG
File size              : 222 KiB

Image
Format                 : JPEG
Width                  : 1 280 pixels
Height                 : 1 024 pixels
Color space             : YUV
Chroma subsampling     : 4:2:0
Bit depth               : 8 bits
Compression mode        : Lossy
Stream size             : 222 KiB (100%)
```

## 8.7 Sharpness Level Monitor and Camera

capture-sharpness.py

- Sharpness level monitor
- Requires opencv and matplotlib Python libraries
- Server application for sharpmon.py

Focusing an object requires adjustment of the optical system. Capturing objects in a macro mode can be challenging regarding a decent focusing. One method to estimate the sharpness level of an image is to calculate its variance of Laplacian. Higher values of variance indicates that there are more sharp edges in the image. A blurry image yield lower variance. Large and smooth color areas decrease the variance although the object may be in focus. This issue can be handled by using ROI, i.e. roi-sharpness.py instead of capture-sharpness.py.

Default OpenCV capture mode (RPI: 640x480) can be overridden with an argument: -hd. In this mode resolution is 1280x720 but the variance is not calculated from FOV, but from a cropped image.

This program is as default in server mode if started from roiapps.py. It provides sharpness data to a client software: sharpmon.py. The server can be started in stand-alone mode with argument -s. Current directory is used as data source directory for monitoring of variance.

By pressing C the program captures pictures with consequent numbering under sharpness sub-directory. It is created under current directory. Pictures are saved in same resolutions as the live preview window but in gray scale. The resolutions are 640x480 and 1280x720. A variance of Laplacian graph is shown and saved (in current directory) after completing capturing and exiting program by pressing ESC. Capture data is also saved as a text file. The names of these files are varfig.png and var.txt.

The program can be launched from roiapps.py or by itself:

```
$ capture-sharpness.py
Monitor sharpness

Default capture mode enabled.
HD mode      : -HD
Server mode: -S

Capture image: C
Toggle server: S
Text color    : TAB
Exit program : ESC

qt5ct: using qt5ct plugin
Server mode: Enabled
```



*A higher value of the variance of Laplacian is an indication of a sharper image.*

## 8.8 ROI Sharpness Level Monitor

roi-sharpness.py

- ROI focusing tool with sharpness monitor
- Requires opencv Python library

This program is very similar to capture-sharpness.py, but ROI is now used to calculate variance of Laplacian. The preview window is small for small ROI areas. A larger extrapolated preview can be used with the toggle button: SPACE.

This program has some run-time options which are listed in the following example:

```
$ roi-sharpness.py
Live ROI sharpness level monitor

Control keys
-----
Toggle ROI/stretch mode: SPACE
Toggle overlay on/off   : Alt_L
Toggle console output   : Ctrl_L
Text color:    TAB
Exit program: ESC

Sharpness:
123
123
123
123
124
```



Live ROI sharpness level monitoring with *roi-sharpness.py*.

## 8.9 Sharpness Live Graph Monitor

sharpmon.py

- Focusing tool: live sharpness graph
- Requires matplotlib Python library

Sharpness if live preview can be monitored with sharpmon.py. As a client software it requires a data server which is capture-sharpness.py. Both programs must be run in same directory which is used as data source directory. If the program is started before server or server mode is enabled in capture-sharpness.py, client waits until data is provided. Thereafter monitoring will start.


The live graph monitor in conjunction with a live preview server enables an easier way to achieve a proper focusing. This is especially emphasized when capturing images when the field of depth is very narrow, e.g. macro photography.

Monitoring can be started by launching the program from roiapps.py launcher or as a standalone program. In both cases it has to be started in the data source directory, where the server application is being executed. This can be accomplished by opening two separate terminals in same directory, where server and client is ran in their respective terminals.

Here is an example how to run the client software:

```
$ sharpmon.py
Sharpness live graph monitor

Data source directory: /home/pi/python/20201021-monitor-
sharpness.py/new
qt5ct: using qt5ct plugin
Waiting for server...
Server found and monitoring started.
```



*Initial focus improved with sharpmon.py live graph client and capture-sharpness.py server. Larger variance indicates a sharper image.*

## 9 Auto Exposure Shutter Speed

expss.py

- Get auto exposure shutter speed
- Optionally get red and blue gains
- Requires a RPI and a camera module

The second step before starting to capture images or recording videos is to determine what is the optimum exposure time. This script returns the actual shutter speed in auto exposure mode. Also it is possible to get the red and blue gains by enabling gains in the code (enable\_gains=True).

Shutter speed is returned in ms and  $\mu$ s units, as shown here:

```
$ expss.py
Auto exposure shutter speed for Raspberry Pi camera 2.x
Shutter speed:    8 ms
Shutter speed: 7533  $\mu$ s
```

## 10 Exposure Bracketing


bracket-exposure.py

- Determine an optimal exposure time by capturing images with different exposures
- 26 JPG files will be created from exposures between 1  $\mu$ s to 0.33 s
- Requires a RPI and a camera module
- Requires raspistill
- Generates and executes scripts (capture commands) which can be executed without Python


A better way to determine optimum exposure time is to do exposure bracketing. The **bracket-exposure.py** captures a series of pictures with different exposure times, starting from 1  $\mu$ s and ending to 0.33 s. From these pictures, it is possible quickly to determine what is the optimum exposure for a imaging project.

Version – 26.10.2020


Here is an example how bracketing exposures works:




1  $\mu$ s




5  $\mu$ s




10  $\mu$ s




25  $\mu$ s



50  $\mu$ s



100  $\mu$ s



200  $\mu$ s



350  $\mu$ s



500  $\mu$ s



750  $\mu$ s



1 ms



2 ms



3.5 ms



5 ms



7.5 ms



10 ms



15 ms




20 ms



35 ms



50 ms



100 ms (too much light for sensor)

The rest exposure times were 150 ms, 200 ms, 250 ms, 300 ms and 330 ms. The camera sensor can not handle so much light. Therefore, these images are almost black (not shown here).

In this example, the composition was illuminated by two non flickering high power LED lamps (550 lx and 440 lx) and with ambient light sources (also non flickering).

Version – 26.10.2020

The usage of this application is very simple which is shown here:

\$ **bracket-exposure.py**

Exposure bracketing program for Raspberry Pi camera v. 2.x (c) Kim Miikki 2019

Select image quality (1...100; default: 90):

Default value selected: 90

List disk and partitions:

NAME	MAJ:MIN	RM	SIZE	RO	TYPE	MOUNTPOINT
sda	8:0	0	223.6G	0	disk	
└─sda1	8:1	0	223.6G	0	part	/media/pi/data
mmcblk0	179:0	0	14.8G	0	disk	
└─mmcblk0p1	179:1	0	2.2G	0	part	
└─mmcblk0p2	179:2	0	1K	0	part	
└─mmcblk0p5	179:5	0	32M	0	part	
└─mmcblk0p6	179:6	0	256M	0	part	/boot
└─mmcblk0p7	179:7	0	12.3G	0	part	/

Path to images (current directory: <Enter>):

Exposure bracketing name: **test**

Select ISO (100, 200, ... 800): **100**

...

## 11 Detect Minimum Exposure Time


dminexp.py

- Detect the minimum exposure time for a RPI camera module
- Requires a RPI and a camera module
- Uses PiCamera library


This application captures initially 2000 pictures from 1  $\mu$ s to 2000  $\mu$ s by increasing exposure time with 1  $\mu$ s for each picture. Consistent results can be obtained by using red and blue gains instead of auto white balance. The images are not saved as default.

As a result a RGB analysis file is created and optionally each images are saved in 320x240 resolution. For an immediate analysis a 300 dpi matplotlib figure is also created, where each color channels (RGB) are represented as functions of exposure time in  $\mu$ s scale.

Some experiments were conducted on 24.6.2020 in order to determine the minimum exposure time for two different camera modules: version 2 (8 MP) and HQ (12.3 MP). Here are the results of these experiments:



*HQ camera module RGB response when red gain=3.16 and blue gain=1.24*



*Camera module (version 2) RGB response in AWB mode*

Fromn these pictures can be detected that HQ camera sensor starts to give respons at 250  $\mu$ s and camera module version 2 almost immediately after 1  $\mu$ s.

Version – 26.10.2020

Here an output of a test run of this application:

```
$ dminexp.py
Raspberry Pi Detect Minimum Exposure Time

List disk and partitions:
NAME      MAJ:MIN RM    SIZE RO TYPE MOUNTPOINT
sda        8:0      0 223.6G  0 disk
└─sda1     8:1      0 223.6G  0 part /media/pi/data
sdb        8:16     1   7.5G  0 disk
└─sdb1     8:17     1   7.5G  0 part /media/pi/INTENSO
mmcblk0   179:0    0  28.8G  0 disk
├─mmcblk0p1 179:1  0   2.4G  0 part
├─mmcblk0p2 179:2  0     1K  0 part
├─mmcblk0p5 179:5  0   32M  0 part
├─mmcblk0p6 179:6  0   256M 0 part /boot
└─mmcblk0p7 179:7  0   26.2G 0 part /

Current directory:
/media/pi/INTENSO/20200624-rpi-ouput

Path to images (current directory: <Enter>):
Project name (default=exp: <Enter>):
Select ISO (100, 200, 320, 400, 500, 640, 800; Default=100):
Default value selected: 100

AWB mode on (Y/N, Default y: <Enter>):
Default selected: AWB enabled

Save captured images (Y/N, Default n: <Enter>):
Default selected: Save images disabled

Capturing images:
1 [3.01457031 2.02445312 3.06352865]
2 [2.98997396 2.02684896 3.04075521]
3 [2.60704427 1.75122396 2.54891927]
4 [2.57395833 1.77282552 2.52416667]
5 [2.5983724 1.75949219 2.53858073]
6 [2.99708333 2.02283854 3.06354167]
7 [2.99395833 2.01251302 3.08651042]
8 [3.00848958 2.00389323 3.07411458]
9 [2.99511719 2.01322917 3.06808594]
10 [2.62606771 1.70393229 2.62039063]
...
```

## 12 Auto White Balance Gains

awb\_gains:

- Get red and blue gains
- Requires a RPI and a camera module

Consistent images can be captured when exposure times, white balance and gains are fixed. For frame rates over 120 fps (8.3 ms shutter speed), automatic exposure and gain control must be turned off [1]. However, the auto white balance can be used even with faster shutter speeds in order to determine red and blue gains. This method is used by **awb\_gains.py**. As default the script uses auto exposure mode, but it can be turned off in the code (`exp_mode_manual="on"`). Here is an example how to get the gains:

```
$ awb_gains.py
Auto white balance gains for Raspberry Pi camera 2.x
Red gain: 1.89 121/64
Blue gain: 1.55 397/256
```

A more accurate method to determine red and blue gains is described in next chapter.

Cited references:

[1] <https://www.raspberrypi.org/documentation/raspbian/applications/camera.md>, 1.4.2020

## 13 White Balance Calibration

calibratecam.py

- Calibrate camera module white balance red and blue gains
- Requires a RPI and a camera module
- Requires raspistill

In order to capture consistent pictures or videos AWB has be turned off. In manual white balance mode red and blue gains must be provided. A fast way to do this is described in previous chapter, but **calibratecam.py** will loop trough all combinations red and blue gains within their ranges, create calibration figures and calculate the optimum gains.

As the first automation step of the white balance calibration, the color data is obtained from three separate (R,G,B) channels in a range of [0, 255] for the investigated gain combinations and thereafter the average values of the data are calculated. Following this step, the absolute differences of all possible 2-tuples (RB, RG, GB) of the averaged data are summed up for different gain combinations. Eventually, the gain combination resulting in the minimum absolute difference is taken as the optimum gain.

Version – 26.10.2020

This application has predefined ranges for red and blue gains 1.0 - 2.0 by step 0.1. The ranges can be overridden with custom steps. As default 11 x 11 directories will be created which results in 121 combination of red and blue gains. A series of pictures are then captured with different exposure times (user selected exposure range) in each directory. RGB color analysis is performed when all series are captured. Color analysis results are stored as calibration figures and in a text file. The later one is used for calculating optimum red and blue gains.

## 13.1 Calibration procedure

This section describes how to do the calibration for red and blue gains. The calibration method is based on white or gray reference color (white or gray card). The goal is to get red, green and blue average sensor response curves as close as possible each other. Only red and blue gains are adjustable. By increasing red or blue gains will decrease the response of the other channels. Hence the calibration becomes an optimizing task. The second requirement for fast shutter speeds (<10-20 ms) is to use flicker free light source(s).

The rough optimum shutter speed has to be determined when the composition with the illumination is ready. This is important when selecting a predefined ranges of exposure times. To get auto exposure shutter speed, expss.py can be executed.

In order to select proper ranges for calibration, awb\_gains reads and returns AWB gain values. These are only rough values for red and blue gains. The calibration will give more accurate, if the optimization task is done in proper ranges and with small steps.

These two steps are recommended to execute before calibration:

```
$ expss.py
Auto exposure shutter speed for Raspberry Pi camera 2.x

Shutter speed:    2 ms
Shutter speed: 2410 µs

$ awb_gains.py
Auto white balance gains for Raspberry Pi camera 2.x

Red gain:  1.85 237/128
Blue gain: 1.51 387/256
```

Next step is to execute the calibration application:

```
$ calibratecam.py
Calibrate Raspberry Pi camera v. 2.x fast (c) Kim Miikki and Alp
Karakoc 2020

Calibration from existing files (Y/N, Default N: <Enter>):
Default selected: Analyze only mode disabled
Select quality (1...100, Default=90: <Enter>):
Default value selected: 90

List disk and partitions:
...

Current directory:
/media/pi/data/20200403-calibration_for_manual
```

Version – 26.10.2020


```
Path to images (current directory: <Enter>):  
Calibration name: manfrotto-white-2xled8-step0.2  
Select ISO (100, 200, 320, 400, 500, 640, 800; Default=100):  
Default value selected: 100  
  
Calculating auto exposure range for calibration:  
Auto shutter speed: 3 ms  
Auto shutter speed: 2524 µs  
Auto shutter speed range for calibration (µs):  
[616, 1233, 1850, 2467, 3083, 3700, 4317]
```

Calibration modes

Md	Pictures	EXP min	EXP max
1	6	50	1000 µs
2	6	1000	15000 µs
3	6	10000	60000 µs
4	6	20000	300000 µs
5	12	50	200000 µs
6	26	1	330000 µs
7	7	616	4317 µs

Select exposure range mode (1...7): 7

Calibration modes 1-4 captures only 6 pictures per series. With default gain ranges and steps the calibration is ready under 10 min by using a Raspberry Pi 4 Model B 4 GB with a USB3 SSD-drive. Mode 6 will last for about 1 h. The red, green and blue average of a picture are in a range of 0 to 255. The calibration application considers a picture as underexposed or overexposed if R,G,B<0.5 or R,G,B>254.5. This protects the calibration against not valid images which would distort the gain values. Additionally it enables the use of a full exposure range, when this kind of images are disposed. The following figures demonstrates, that all images under 100 µs are disposed as underexposed:



*Uncalibrated and calibrated sensor RGB channel curves in logarithmic scale.*

Version – 26.10.2020

Calibration mode 7 reads the auto exposure value and generates the following exposure array:

[ 0.25\*ss, 0.50\*ss, 0.75\*ss, ss, 1.25\*ss, 1.50\*ss, 1,75\*ss ]

where ss is the shutter speed.

The mode 7 normally captures pictures which are properly exposed, and are valid for calibration. If consisted calibration with the same exposure time is required, a predefined array (i.e. exp\_fast or exp\_medium1) could be used in the code by replacing the original exposure times with exposure times calculated from the auto exposure value.

In the forth stage default ranges for red and blue gains are accepted or modified:

Default calibration ranges:

Red gain range: 1.0-2.0

Red gain step: 0.1

Blue gain range: 1.0-2.0

Blue gain step: 0.1

Accept default ranges (Y/N, Default Y: <Enter>): **n**

Current ranges disabled

Select red gain min (1.0...2.0, Default=1.0: <Enter>): **1.6**

Select red gain max (1.6...2.0, Default=2.0: <Enter>): **1.8**

Select red gain step (0.001...0.2, Default=0.1: <Enter>): **0.02**

Select blue gain min (1.0...2.0, Default=1.0: <Enter>): **1.3**

Select blue gain max (1.3...2.0, Default=2.0: <Enter>): **1.5**

Select blue gain step (0.001...0.2, Default=0.1: <Enter>): **0.02**

Select scale type (linear, log; Default=linear):

Default value selected: linear

Pictures are captured in stage 5 with the raspistill program. Normally the duration of this stage is from few minutes up to 1 hour. In stage 6 color analysis is done for each series of pictures and calibration figures are saved into a figures directory. In the last stage optimum red and blue gains are calculated. Here is a part of a calibration log file, where the results are presented:

...

Calibration images: 847



Optimal r\_gain: 1.66

Optimal b\_gain: 1.44


Total distance: 11.140924479166713

Time elapsed: 0:11:12.595477

The following pictures demonstrates the difference of uncalibrated and calibrated gains:



*Uncalibrated white card picture and sensor RGB curves (gains: red 1.0 and blue 1.0).*



Calibrated white card picture and sensor RGB curves (gains: red 1.66 and blue 1.44).

## 13.2 Calibration with ROI

If the the white card or calibration area is too small, the camera module has to be closer the object or ROI must be applied. The field of view can be narrowed easily with the ROIs variable in the code:

```
roi_x0=0.0  
roi_y0=0.0  
roi_w=1.0  
roi_h=1.0
```

The default values gives full field of view. All values are normalized from 0.0 to 1.0. Two first variables defines the coordinates where ROI starts from the upper left corner. The latter variables defines width and height for ROI. Raspistill can be used in order to get desired ROI like the following example:

```
raspistill -t 0 -roi 0.25,0.25,0.5,0.5 (middle area of FOV with 25 % margins)
```

### 13.3 Analyze only mode

It is possible to do post-calibration from existing calibration pictures. Optimum gains can be calculated very fast if the calibration file exist (rgb-calibration\_name\*.txt). In such case, the gains can be calculated very fast with optimum\_gains.py. However, if the calibration file is missing, change of scale type is desired (log → linear or linear → log) or calibration figures has to be re-created, then campreview.py can be executed in *analyze only mode*.

The Analyze only mode asks path to images (calibration base directory), calibration name and the scale type. Thereafter color analysis is performed for all valid calibration directories, which mean that the calibration name must be same as the calibration directories base name followed by \_rgain,bgain, where rgain and bgain are positive numbers. All invalid directory names are disposed. The calibration program will create automatically these calibration directory names correctly when analyze only mode is disabled.

At the final stage optimum red and blue gains are calculated.

## 14 Get Optimum Gains from a Calibration File

optimum\_gains.py

- Get optimal red and blue gains from a calibration file

This utility reads a calibration file (rgb-project\_name.txt), which can be produced by calibratecam.py application. Optimal red and blue gains are calculated when the calibration data is read. Here is an example how to execute optimal\_gains.py:

```
$ optimal_gains.py rgb-manfrotto-white-2xled8-step0.02_iso100.txt
Calibration images: 847
Optimal r_gain = 1.66
Optimal b_gain = 1.44
Total distance = 11.140924479166713
```

## 15 Capturing Pictures in Manual Mode

These applications are designed to capture pictures manually by pressing the space bar. The reason for two programs is that there is a different delay before a new picture can be captured. A live preview will lead to longer time before a new picture can be captured. That is the reason for the camera application without a preview.

### 15.1 Capturing Pictures with Preview Enabled

`capturepics-preview.py`

- Camera preview is enabled
- Captures lossless PNG pictures by pressing space bar
- Auto numbering of captures
- Delay before capturing next picture is several seconds
- Requires a RPI and a camera module
- Uses PiCamera library

This application would be very convenient if the time between captures would be smaller. The application can be used when the composition must be accurate and the amount of captures is small.

Here is an example how to run this application:

```
$ capturepics-preview.py
Raspberry Pi capture pictures
Select image quality (1...100; default: 90):
Default value selected: 90

List disk and partitions:
NAME      MAJ:MIN RM    SIZE RO TYPE MOUNTPOINT
sdb        8:16   0 223.6G  0 disk
└─sdb1     8:17   0 223.6G  0 part /media/pi/data
mmcblk0   179:0   0  14.8G  0 disk
├─mmcblk0p1 179:1   0    2.2G  0 part
├─mmcblk0p2 179:2   0     1K  0 part
├─mmcblk0p5 179:5   0    32M  0 part
├─mmcblk0p6 179:6   0   256M  0 part /boot
└─mmcblk0p7 179:7   0   12.3G 0 part /

Path to images (current directory: <Enter>):
Project name (default=pic: <Enter>):
Select ISO (100, 200, ... 800): 100
Select exposure time (1...330000) µs: 35000
```

Version – 26.10.2020

```
Select first frame number (default=1: <Enter>) :  
Default value selected: 1  
Select digits (min=1, default=4: <Enter>) :  
Default value selected: 4  
No artist.txt file  
Full screen and cropped preview (Y/N, default: N <ENTER>)  
Default selected  
  
Start capturing images: ENTER  
Capture image: SPACE  
Exit program: ESC  
  
Capture mode enabled.  
pic_0001  
pic_0002
```

ESC key pressed → termination of the application

## 15.2 Camera with Preview

camera.py

- Camera preview is enabled
- Captures pictures by pressing ENTER
- Auto numbering of captures
- Time between captures is about 1 second
- Requires a RPI and a camera module
- Requires raspistill
- Generates and executes scripts (capture commands) which can be executed without Python

This application captures pictures much faster than capturepics-preview.py. However, the captured pictures are compressed in a lossy JPG format. The program generates a raspistill command which can be ran without Python. Following example shows how to run this program:

```
$ camera.py
Raspberry Pi camera

Select image quality (1...100, Default=90: <Enter>):
Default value selected: 90

List disk and partitions:
NAME      MAJ:MIN RM  SIZE RO TYPE MOUNTPOINT
mmcblk0    179:0   0 29.7G  0 disk
└─mmcblk0p1 179:1   0  256M  0 part /boot
└─mmcblk0p2 179:2   0 29.5G  0 part /

Current directory:
/home/pi/pics

Path to images (current directory: <Enter>):
Project name (default=pic: <Enter>):
Select ISO (100, 200, 320, 400, 500, 640, 800; Default=100):
Default value selected: 100

Auto exposure on (Y/N, Default y: <Enter>):
Default selected: EXP auto enabled

AWB mode on (Y/N, Default y: <Enter>):
Default selected: AWB enabled

Select analog gain (0.0...12.0, Default=1.0: <Enter>):
Default value selected: 1.0
```

Version – 26.10.2020

```
Select digits (1...8, Default=4: <Enter>):
Default value selected: 4
Select first frame (1...9999, Default=1: <Enter>):
Default value selected: 1

"raspistill" Camera App (commit f73fca015d42 Tainted)

Camera Name imx477
Width 4056, Height 3040, filename pic_%04d.jpg
Using camera 0, sensor mode 0

GPS output Disabled

Quality 90, Raw no
Thumbnail enabled Yes, width 64, height 48, quality 35
Time delay 0, Timelapse 0
Link to latest frame enabled no
Full resolution preview No

Capture method : Capture on keypress

Preview Yes, Full screen Yes
Preview window 0,0,1024,768
Opacity 255
Sharpness 0, Contrast 0, Brightness 50
Saturation 0, ISO 100, Video Stabilisation No, Exposure
compensation 0
Exposure Mode 'auto', AWB Mode 'auto', Image Effect 'none'
Flicker Avoid Mode 'off'
Metering Mode 'average', Colour Effect Enabled No with U = 128, V
= 128
Rotation 0, hflip No, vflip No
ROI x 0.000000, y 0.000000, w 1.000000 h 1.000000
Camera component done
Encoder component done
Starting component connection stage
Connecting camera preview port to video render.
Connecting camera stills port to encoder input port
Press Enter to capture, X then ENTER to exit

Opening output file pic_0001.jpg
Enabling encoder output port
Starting capture 1
Finished capture 1
Press Enter to capture, X then ENTER to exit
```

Version – 26.10.2020

```
Opening output file pic_0002.jpg
Enabling encoder output port
Starting capture 2
Finished capture 2
Press Enter to capture, X then ENTER to exit
x
Opening output file pic_0003.jpg
Enabling encoder output port
Starting capture 3
Finished capture 3
Closing down
Close down completed, all components disconnected, disabled and
destroyed
```

Capturing pictures is exited by pressing X followed with ENTER.

A log file is created of the selections. This example generated the following file:

**pic.log**

Log created on 2020.10.26-22:00:12

File path: Not defined

Capture pictures parameters:

Resolution: 4056x3040

Sensor: imx477

Quality: 90

Compression: lossy

ISO value: 100

Exposure: auto

AWB mode: Enabled

Analog gain: 1.0

Start frame: 1

Digits: 4

First file name: pic\_0001.jpg

Capture command:

```
raspistill -v -t 0 -q 90 -ISO 100 -ag 1.0 -k -fs 1 -o pic_%04d.jpg
```

## 15.3 Capturing Pictures without Preview

capturepics.py

- Camera preview is disabled
- Captures pictures by pressing space bar
- Auto numbering of captures
- Time between captures is about 1 second
- Requires a RPI and a camera module
- Requires raspistill
- Generates and executes scripts (capture commands) which can be executed without Python

The capturepics.py generates commands, which will capture pictures by using raspistill program. The delay before capturing a new picture is much smaller than with the capturepics-preview.py. The drawback is that there is no preview. Therefore, the composition must be done before using this application.

This example shows how to use capturepics.py:

```
$ capturepics.py

Raspberry Pi capture pictures
Select image quality (1...100; default: 90):
Default value selected: 90

List disk and partitions:
NAME      MAJ:MIN RM    SIZE RO TYPE MOUNTPOINT
sdb        8:16   0 223.6G  0 disk
└─sdb1     8:17   0 223.6G  0 part /media/pi/data
mmcblk0   179:0   0 14.8G  0 disk
├─mmcblk0p1 179:1   0    2.2G  0 part
├─mmcblk0p2 179:2   0      1K  0 part
├─mmcblk0p5 179:5   0    32M  0 part
├─mmcblk0p6 179:6   0   256M  0 part /boot
└─mmcblk0p7 179:7   0   12.3G 0 part /

Path to images (current directory: <Enter>):
Project name (default=pic: <Enter>):
Select ISO (100, 200, ... 800): 100
Select exposure time (1...330000) µs: 35000
Select first frame number (default=1: <Enter>):
Default value selected: 1
Select digits (min=1, default=4: <Enter>):
```

Version – 26.10.2020

```
Default value selected: 4
No artist.txt file

Start capturing images: ENTER
Capture image: SPACE
Exit program: ESC

Capture mode enabled.

pic_0001
pic_0002
pic_0003
pic_0004
pic_0005
```

**ESC key pressed → termination of the application**

The log file which contains data about to project, looks like this:

```
Log created on 2019.12.29-18:14:07

File path: Not defined

Artist:
Capture pictures parameters:
Quality: 90
ISO value: 100
Exposure: 35000 µs
Start frame: 1
Digits: 4
First file name: pic_0001.png

raspistill -n -t 1 -ISO 100 -q 90 -ss 35000 -bm -drc high -o pic_0001.png
raspistill -n -t 1 -ISO 100 -q 90 -ss 35000 -bm -drc high -o pic_0002.png
raspistill -n -t 1 -ISO 100 -q 90 -ss 35000 -bm -drc high -o pic_0003.png
raspistill -n -t 1 -ISO 100 -q 90 -ss 35000 -bm -drc high -o pic_0004.png
raspistill -n -t 1 -ISO 100 -q 90 -ss 35000 -bm -drc high -o pic_0005.png
```

## 16 Time-Lapse Photography

timelapse.py

- Capture pictures in time-lapse mode
- Minimum interval between captures is 1 s
- Pictures are stored in JPG format
- Requires a RPI and a camera module
- Requires raspistill
- Generates and executes a script (capture command) which can be executed without Python

The idea of time-lapse photography can be easily demonstrated by melting an ice cube:



0 min



2 min



4 min



6 min



8 min



10 min



12 min



14 min



16 min



18 min



20 min



22 min



24 min



26 min



28 min



30 min



32 min

Capture parameters for the pictures above:

Time-lapse parameters:

Quality: 90

ISO value: 100

Exposure: 30000

Duration: 1800000

Interval: 120000

Start frame: 1

Although this application provides a preview option, the use of it should be considered when using a short interval. Especially 1 s interval time could result in loss of frames or delayed capture times. Other factors that increases loss of frames: running time-lapse on a slower computer (RPI 3), large screen resolution and long exposure times (>20 ms). Hence, the preview is disabled as default on a RPI 3.

The following example shows what kind of questions has to be answered before starting to capture 10 s time-lapse with 1 s interval:

```
$ timelapse.py
Time-lapse program for Raspberry Pi camera v. 2.x (c) Kim Miikki
2019
Select image quality (1...100; default: 90): 90

List disk and partitions:
NAME      MAJ:MIN RM    SIZE RO TYPE MOUNTPOINT
sda        8:16   0 223.6G  0 disk
└─sda1     8:17   0 223.6G  0 part /media/pi/data
mmcblk0   179:0   0 14.8G  0 disk
├─mmcblk0p1 179:1   0  2.2G  0 part
├─mmcblk0p2 179:2   0    1K  0 part
├─mmcblk0p5 179:5   0    32M  0 part
├─mmcblk0p6 179:6   0   256M  0 part /boot
└─mmcblk0p7 179:7   0 12.3G  0 part /

Path to images (current directory: <Enter>):
Time-lapse project name: tl
Select ISO (100, 200, ... 800): 100
Select exposure time (1...330000) µs: 35000
Select interval (1...86400) s: 1
Select time-lapse duration (1...31536000) s: 10

Start time-lapse shooting now (Y/N, Default Y: <Enter>):
Default selected: starting the time-lapse shooting.

...
```

## 17 Video Recording

fpsvideo.py

- Record videos in slow, normal or high speed (up to 200 FPS)
- Requires a RPI and a camera module
- Requires raspivid
- Generates and executes a script (recording command) which can be executed without Python

Although it is possible to record videos with the RPI camera module up to 1000 frames per second [1], **fpsvideo.py** uses standard RPI **raspivid** application which limits the FPS to 200. This can be done without compiling source codes and playing with raw Bayer format frames.

Here is an example of a 90 FPS at 1280x720 (720 p) what raspivid is capable to produce:



Frame: 420



Frame: 435



Frame: 445



Frame: 455



Frame: 463



Frame: 464



Frame: 465



Frame: 466



Frame: 467



Frame: 468




Frame: 469




Frame: 470


Version – 26.10.2020



Frame: 471



Frame: 475



Frame: 480

The video slowdown rate is 3.6 when the normal play speed is 25 FPS. The capture parameters are shown below:

Log created on 2019.12.31-12:27:01

File path: Not defined

Files:

Video: probe-1280x720\_90fps\_11111ss\_30s.h264  
PTS: probe-1280x720\_90fps\_11111ss\_30s.pts  
Log: probe-1280x720\_90fps\_11111ss\_30s.log  
REC: probe-1280x720\_90fps\_11111ss\_30s.rec

FPS video parameters:

Sensor mode: 6

Resolution: 1280x720

Exposure: 11111  $\mu$ s

FPS: 90

AWB: Auto

Duration: 30 s

Preview: on

Record video:

```
raspivid -md 6 -w 1280 -h 720 -ss 11111 -fps 90 -t 30000 -v -pts
probe-1280x720_90fps_11111ss_30s.pts -o probe-
1280x720_90fps_11111ss_30s.h264 2>&1 | tee probe-
1280x720_90fps_11111ss_30s.rec

mkvmerge -o probe-1280x720_90fps_11111ss_30s.mkv probe-
1280x720_90fps_11111ss_30s.h264 2>&1 | tee -a probe-
1280x720_90fps_11111ss_30s.rec
```

In this experiment, compressed air was used to make the probe to fall. The settle down time for the probe, after it started to fall was about 0.7 s. The frames were extracted by using FFmpeg [2].

This application generates scripts, which will start raspivid and mkvmerge [3]. The first program will record the video and the second convert it to a MKV file.

If normal video playback is 25 FPS, then the slowdown (depending on the video mode), is at maximum FPS:

<b>Md</b>	<b>Video resolution</b>	<b>Maximum FPS</b>	<b>Video slowdown</b>
1	1920x1080	30	1.2
2	1920x1080	15	0.6
3	1920x1080	15	0.6
4	1640x1232	40	1.6
5	1640x922	40	1.6
6	1280x720	90	3.6
7	640x480	200	8

*Video slowdown at 25 FPS*

Standard raspistill command for composition is not enough before recording a video. RPI application vidpreview.py will do the job with ROI.

This application creates some additional files which can be useful for debugging or if exact times for frames are required:

LOG All selections and video commands are stored in this file

PTS Save timestamp information to the specified file

REC Redirect stdout and stderr to the REC file

Videos are stored at least as H.264 and (optionally) transformed to MKV.

The requested FPS is not necessary what is acquired. Hence a timing correction is required. The following formula calculates the correct time for one frame

$$t_f = \frac{FPS_{requested}}{FPS_{reference}} \cdot \frac{\text{recorded video duration}}{\text{frames recorded}}$$

where  $FPS_{reference}$  is the normal playback speed (25 frames/s).

Version – 26.10.2020

## Running the Application

This example shows how to run the application:

```
$ fpsvideo.py
FPS video program for Raspberry Pi camera v. 2.x (c) Kim Miikki
2019

List disk and partitions:
NAME      MAJ:MIN RM    SIZE RO TYPE MOUNTPOINT
sda        8:0      0 223.6G  0 disk
└─sda1     8:1      0 223.6G  0 part /media/pi/data
mmcblk0   179:0    0 14.8G  0 disk
├─mmcblk0p1 179:1  0  2.2G  0 part
├─mmcblk0p2 179:2  0    1K  0 part
├─mmcblk0p5 179:5  0    32M  0 part
├─mmcblk0p6 179:6  0   256M  0 part /boot
└─mmcblk0p7 179:7  0 12.3G  0 part /

Path to images (current directory: <Enter>):
Video project name: test
Select bitrate (1-25000000 bits/s, automatic: <Enter>):
Automatic bitrate selected.

Video modes
1 1920x1080 16:9 30
2 1920x1080 4:3 15
3 1920x1080 4:3 15
4 1640x1232 4:3 40
5 1640x922 16:9 40
6 1280x720 16:9 90
7 640x480 4:3 200
8 640x480 4:3 180

Select video mode (1...8): 7
Select FPS: (40...200, Default 200: <Enter>):
Default selected: 200 FPS
Select exposure time (1...5000) µs: 5000
Select video duration (1...31536000) s: 2

Enable preview (Y/N, Default N: <Enter>): y
Preview enabled
Convert to MKV file (Y/N, Default Y: <Enter>):
Default selected: MKV conversion enabled
Start recording now (Y/N, Default Y: <Enter>):
Default selected: starting to record.
```

## Version – 26.10.2020

```
raspivid -md 7 -w 640 -h 480 -ss 5000 -fps 200 -t 2000 -ex off -ag  
1.0 -dg 1.0 -awb off -awbg 1,1 -v -pts test-  
640x480_200fps_5000ss_2s.pts -o test-640x480_200fps_5000ss_2s.h264  
2>&1 | tee test-640x480_200fps_5000ss_2s.rec  
  
mkvmerge -o test-640x480_200fps_5000ss_2s.mkv test-  
640x480_200fps_5000ss_2s.h264 2>&1 | tee -a test-  
640x480_200fps_5000ss_2s.rec  
  
"raspivid" Camera App (commit )  
  
Camera Name imx219  
Width 640, Height 480, filename test-640x480_200fps_5000ss_2s.h264  
Using camera 0, sensor mode 7  
  
GPS output Disabled  
  
bitrate 17000000, framerate 200, time delay 2000  
H264 Profile high  
H264 Level 4  
H264 Quantisation level 0, Inline headers No  
H264 Fill SPS Timings No  
H264 Intra refresh type (null), period -1  
H264 Slices 1  
Wait method : Simple capture  
Initial state 'record'  
  
Preview Yes, Full screen Yes  
Preview window 0,0,1024,768  
Opacity 255  
Sharpness 0, Contrast 0, Brightness 50  
Saturation 0, ISO 0, Video Stabilisation No, Exposure compensation 0  
Exposure Mode 'off', AWB Mode 'off', Image Effect 'none'  
Flicker Avoid Mode 'off'  
Metering Mode 'average', Colour Effect Enabled No with U = 128, V = 128  
Rotation 0, hflip No, vflip No  
ROI x 0.000000, y 0.000000, w 1.000000 h 1.000000  
Camera component done  
Encoder component done  
Starting component connection stage  
Connecting camera preview port to preview input port  
Starting video preview  
Connecting camera video port to encoder input port  
Opening output file "test-640x480_200fps_5000ss_2s.h264"  
Opening output file "test-640x480_200fps_5000ss_2s.pts"  
Enabling encoder output port  
Starting video capture  
Finished capture  
Closing down  
Close down completed, all components disconnected, disabled and destroyed
```

Version – 26.10.2020

```
mkvmerge v31.0.0 ('Dolores In A Shoestand') 32-bit
'test-640x480_200fps_5000ss_2s.h264': Using the demultiplexer for the format
'AVC/h.264'.
'test-640x480_200fps_5000ss_2s.h264' track 0: Using the output module for the
format 'AVC/h.264 (unframed)'.
The file 'test-640x480_200fps_5000ss_2s.mkv' has been opened for writing.
Warning: 'test-640x480_200fps_5000ss_2s.h264' track 0: This AVC/h.264 track's
timing information indicates that it uses a variable frame rate. However, no
default duration nor an external timestamp file has been provided for it, nor
does the source container provide timestamps. The resulting timestamps may not
be useful.
Progress: 100%
The cue entries (the index) are being written...
Multiplexing took 0 seconds.
```

Cited references:

- [1] <https://github.com/6by9/raspiraw>, 1.1.2020
- [2] <https://www.ffmpeg.org>, 2.1.2020
- [3] <https://mkvtoolnix.download/doc/mkvmerge.html>, 2.1.2020

## 18 Creating Videos from Pictures

gtlvideo.py

- Generates videos in MKV format from PNG, JPG and CR2 pictures
- Python version 3.5 or higher is required
- Requires exifread, PIL, numpy and pandas Python libraries
- Requires FFmpeg and darktable\_cli (if using CR2 files)
- Generates and executes a script (recording command) which can be executed without Python

This application is the most complicated of these RPI camera applications. PNG, JPG or CR2 files are required for video creation. The program search for those files in current directory. If it finds same amount of CR2, PNG and JPG files, the priority for video creation is CR2 > PNG > JPG. The images must be numbered consecutively (with leading zeros) before the extension and the file name have to be constant before the numbering. The amount of image files (PNG, JPG or CR2) are counted and checked that there are no missing or additional frames. Otherwise to program will terminate. The program assumes that all frames have the same resolution.

In order to create a video of pictures, aspect ratio for source and target is one of the most important thing to consider. The easiest thing is to crop images without scaling. In this case, an arbitrary A/R can be selected. In crop and scale mode the maximum amount of information will be saved when either source width or height will be constant, and cropping have to be done on the opposite axis, in order to get same geometry for source and destination resolution.

Version – 26.10.2020

However, the program start by asking for the project name. By pressing Enter the default project name will be *video*. The next question is about video mode. Possible choices are landscape or portrait (default is landscape).

A dynamic table of video modes will be presented on the basis of the picture resolution. This example illustrates this (resolution was 1024x768):

Video modes

0 Native	1024x768	1024:768
9 SD	720x576	16:9
10 XGA	1024x768	4:3
11 VGA	640x480	4:3
12 GIF	320x200	4:3
13 Custom	?x?	x:y

Select video mode (Default mode is: 10 = 1024x768 <Enter>):

Next selection is how to crop the images when producing a video. Default mode is C&R on order to save as much information as possible. The images on the following pages will illustrate what different cropping means.



Original picture 1

Version – 26.10.2020


Predefined crop areas in Crop mode:



Top and Left




Top and Center



Top and Right



Center and Left




Center and Center




Center and Right



Bottom and Left



Bottom and Center




Bottom and Right

Version – 26.10.2020

Predefined crop areas in Crop & Resize mode:



Top crop



Horizontal center crop



Bottom crop


Version – 26.10.2020



Left crop



Center vertical crop



Right crop

Custom crop area:



Original picture 2



ROI: Crop size 640x480 and start coordinates: (1111, 315)

The menus depends of the source and target geometry of resolutions, and choices done. Therefore it is not useful to show every possible menu in this manual.

After crop menus (if cropping was required) the program asks for video FPS (default is 25). Then the duration of the video is calculated and shown. Next decision has to be made on CRF (video quality; default is 23). Lower value is better but the size of video file will increase if better quality is required.

Finally, a summary of selections is given, and the final question asks if video creation should be done.

Two sub directories will be created: png and video. All crops and image conversion files will be stored in the first one. The video directory consist of the video and log files.

This example illustrates how to run the program:

```
$ gtlvideo.py
Generate time-lapse video from images
Version 0.921 (beta) (C) Kim Miikki 2020

Python version: 3.5

Scanning supported image files in current directory...

CR2 info:
Files: 0
Width: 0
Height: 0

PNG info:
Files: 49
Width: 5202
Height: 3464

JPG info:
Files: 0
Width: 0
Height: 0
```

Version – 26.10.2020

Sample file name: IMG\_5010.png  
Digits before file extension: 4  
Default picture format: PNG

Select project name (Default: video <Enter>) : **sunset**

Project name: sunset

Video name : sunset.mkv

Select video mode (landscape=L, portrait=P, Default: Landscape <Enter>):

Landscape video mode selected

Video modes

0 Native	5202x3464	5202:3464
2 4K/DCI	4096x2160	256:135
3 4K/UHD	3840x2160	16:9
4 2K	2560x1440	16:9
5 Full HD	1920x1080	16:9
6 Pi/md4	1640x1232	4:3
7 Pi/md5	1640x922	16:9
8 HD	1280x720	16:9
9 SD	720x576	16:9
10 XGA	1024x768	4:3
11 VGA	640x480	4:3
12 GIF	320x200	4:3
13 Custom	?x?	x:y

Select video mode (Default mode is: 0 = 5202x3464 <Enter>) : **5**

Crop & Resize or only Crop?

Select Crop & Resize or only Crop (C&R=Y, C=N, Default: C&R <Enter>):

C&R mode selected

Crop mode: vertical

Image original size: 5202 x 3464

Image size before scaling: 5202 x 2926

Video size after scaling: 1920 x 1080

0 = Middle crop

1 = Top crop

2 = Bottom crop

3 = Custom crop start Y (0...537)

Select crop mode (Default: 0) ? **2**

Version – 26.10.2020

Standard video frame rates: 24, 25, 30, 48, 50 and 60  
Select video FPS (1...60, Default=25 <Enter>) : **10**

Video information

Frames: 49

FPS: 10

Duration: 4.9 s

Select 10 frames/s (Y/N, Default: Y <Enter>) :  
Default FPS selected

Constant Rate Factor: 0 (lossless) - 18 - 23 (default) - 28 - 51  
(worst)

Select video CRF for x264 (0...51, Default=23 <Enter>) :  
Default CRF selected

"/home/.../png/"

-----

Summary of selections:

Program version: 0.921 (beta)

Project name: sunset

Video name: sunset.mkv

Video resolution is smaller than image size

Crop mode: crop and resize

Crop direction: vertical

Crop selection: Bottom crop

Crop coordinates: (0,537)-(5201,3463)

Crop geometry error: -0.00 %

Image size: 5202x3464

Cropped image size: 5202x2926

Video size: 1920x1080

Picture geometry (h/w): 0.6658977316416763

Cropped image geometry (h/w): 0.5624759707804691

Video geometry (h/w): 0.5625

File format: PNG

File sample name: IMG\_5010.png

First new file name: IMG\_4980.png

Working path: /home/...

PNG path: /home/.../png/

Video and log path: /home/.../video/

Video name: sunset.mkv

Version – 26.10.2020

```
Log name:                      sunset.log
File format digits:            4
First frame:                   4980
Last frame:                    5028
Calculated number of frames:  49
Files:                         49
FPS:                           10
Duration:                      4.9 s
Constant Rate Factor (CRF):   23

Stage 1: PNG→PNG
for i in "/home/.../*.*.png ; do ffmpeg -y -i "$i" -vf
crop=5202:2926:0:537,scale=1920:1080 "/home/.../png/"sunset-$
(basename "$i" ".png")".png ; done

Stage 2: Create video
ffmpeg -y -r 10 -start_number 4980 -i "/home/.../png/sunset-IMG_"
%04d.png" -c:v libx264 -crf 23 "/home/.../video/sunset.mkv"

Are you sure you want to proceed (Y/N, Default=Y <Enter>) ? y

...
Stage 1 duration: 0:01:20.655601
Stage 2 duration: 0:00:04.607428
```

## 19 RGB Color Analysis

rgbinfo.py


- Calculate RGB and BW means of PNG and JPG pictures
- Requires numpy and opencv Python libraries
- RPI is not required

Current directory is scanned and color analysis is carried out if the picture is in PNG or JPG format. Here is an example of an experiment where the palm tree was illuminated by an infrared heater. The RPI camera module used was v. 2.x NoIR. The sample picture's exposure time was 20 ms.



*VIS and IR illuminated composition at 20 ms exposure.*

An exposure bracketing experiment was performed and here is the result as a function of time:



*Color analysis performed by rgbinfopy.*

Version – 26.10.2020

This program calculates the average R, G and B channels and BW of each picture in current directory.

Here is an example run of the program:

```
$ rgbinfo.py
RGBinfo 1.0, (c) Kim Miikki 2019

Analyzing:
20190322_102606.png: 4032x2268
20190322_102611.png: 4032x2268
20190322_102612.png: 4032x2268

Pictures analyzed: 3
Time elapsed: 0:00:01.290984

$ cat rgb-png.txt
picture_name;rgb_avg;r_avg;g_avg;b_avg;rgb_ratio;r_ratio;g_ratio;b_ratio
20190322_102606.png;106.70739222901095;95.30768676426332;104.93878688306599;119.
87570303970354;0.41846036168239586;0.3737556343696601;0.41152465444339603;0.4701
0079623413153
20190322_102611.png;126.4928493859821;119.13333105876096;125.56441917044596;134.
7807979287394;0.4960503897489494;0.46718953356376847;0.4924094869429253;0.528552
1487401544
20190322_102612.png;125.87577109461755;118.75658915186445;124.93207055198623;133
.93865358000195;0.49363047488085315;0.46571211432103704;0.4899296884391617;0.525
2496218823606

Pictures analyzed:;3
Time elapsed:;0:00:01.290984
```

## 20 Splitting RGB Channels into Separate Images


The RPI camera software suite provides tools to split images into RGB channels in two different ways. The first one splits images into 3 channel red, green and blue colored images. The second one splits them into 1 channel gray scale images, where the RGB channel information is stored as a filename prefix of the color split image.

### 20.1 Splitting RGB Channels into separate RGB Images

rgbsplit.py

- Split RGB channels of PNG or JPG pictures into separate images
- Requires numpy and cv2 Python libraries
- RPI is not required


An experiment was conducted in Ylläs, Lapland, Finland on 16.7.2019 (by shooting in time-lapse mode) with a Canon 7D camera. The interval between pictures was 20 s. This sample shows how rgbsplit.py can be used to split images into red, green and blue color channel images, and black & white images:



sunset-IMG\_5010.png



sunset-IMG\_5011.png



sunset-IMG\_5012.png




R-sunset-IMG\_5010.png




R-sunset-IMG\_5011.png



R-sunset-IMG\_5012.png



G-sunset-IMG\_5010.png



G-sunset-IMG\_5011.png



G-sunset-IMG\_5012.png

Version – 26.10.2020



B-sunset-IMG\_5010.png



B-sunset-IMG\_5011.png



B-sunset-IMG\_5012.png



BW-sunset-IMG\_5010.png



BW-sunset-IMG\_5011.png



BW-sunset-IMG\_5012.png

This program does not require a RPI. The only requirements is that the pictures have to be in PNG or JPG format. R-, G-, B- and BW- prefixed images are stored in the same directory where the source images are located.

This conversion was executed this way:

```
$ rgbsplit.py
RGBsplit 1.0, (c) Kim Miikki 2019

Splitting color channels:
sunset-IMG_5010.png: 5202x3464
sunset-IMG_5011.png: 5202x3464
sunset-IMG_5012.png: 5202x3464

Pictures processed: 3
Time elapsed: 0:00:08.240715
```

## 20.2 Splitting RGB Channels into Separate Gray Scale Images

bw-rgbsplit.py

- Split RGB channels of PNG or JPG pictures into separate gray scale images
- Requires numpy and cv2 Python libraries
- RPI is not required

This program splits RGB color images into 8-bit gray scale images, like the following example shows:



Original 3 channel RGB picture



Red channel as 8-bit gray scale image



Green channel as 8-bit gray scale image



Blue channel as 8-bit gray scale image

The color channel information is stored in file names as prefixes:

BWR-: Red channel

BWG-: Green channel

BWB-: Blue channel

Version – 26.10.2020

Otherwise original file names are stored directly after these prefixes. The program should be executed in the same directory, where the pictures are located:

**\$ bw-rgbsplit.py**

BW-RGBsplit 1.0, (c) Kim Miikki 2020

Splitting color channels:

20200406\_090114.jpg: 4032x3024

Pictures processed: 1

Time elapsed: 0:00:00.644501

## 21 Combining RGB split Images into Color Images

All of these color channel separation operations can be reversed by merging color channels back into RGB color images. Normally merging is done after enhancing etc. the individual color channels.

### 21.1 Combining 3 Channel RGB split Images into Color Images

rgbcombine.py

- Merge RGB split 3 channel PNG or JPG images into color images
- Requires numpy and cv2 Python libraries
- RPI is not required

This program search for B-, G- and R- prefixed images in current directory, and merge them into color images. The color split images must be 3 channel RGB color split images. Here is an example how to use the program:

```
$ ls -1
B-20200406_090114.jpg
G-20200406_090114.jpg
R-20200406_090114.jpg

$ rgbcombine.py
RGBcombine 1.0, (c) Kim Miikki 2020

Combining color channels:
20200406_090114.jpg: 4032x3024

Pictures processed: 1

Time elapsed: 0:00:00.858192
```

## 21.2 Combining 1 Channel RGB split Images into Color Images

bw-rgbcombine.py

- Merge RGB split 1 channel PNG or JPG images into color images
- Requires numpy and cv2 Python libraries
- RPI is not required

This program search for BWB-, BWG- and BWR- prefixed images in current directory, and merge them into color images. The color split images must be 1 channel gray scale images. The following example demonstrate how to use this program:

```
$ ls -1
BWB-20200406_090114.jpg
BWG-20200406_090114.jpg
BWR-20200406_090114.jpg

$ bw-rgbcombine.py
BW-RGBcombine 1.0, (c) Kim Miikki 2020

Combining color channels:
20200406_090114.jpg: 4032x3024

Pictures processed: 1

Time elapsed: 0:00:00.600683
```

## 22 Batch Resize Images

resize-batch.py

- Batch resize images
- Requires opencv Python library

This program resizes images from the working directory to a sub-directory named `resize_x` or `resize_y`. By default resizing is width based and new height is calculated based on original A/R of the image. As default `cv2.INTER_CUBIC` method is used when resizing images. It can be overridden by changing the value. Valid methods are listed in an array named `inter_methods`.

Usage of this program and the generated output structure can be seen from following example:

Version – 26.10.2020

```
$ resize-batch.py
Image batch resize tool
Override default options (Y/N, Default N: <Enter>):
Default selected: override disabled
Resize by width (Y/N, Default Y: <Enter>):
Default selected: width enabled
Select width (1...10000, Default=1600: <Enter>): 640

Resize options
-----
Convert images to PNG: no
A/R round method: int
Resize method: 2
Only landscape images will be resized

Resized: ptfe-h2o-frame00000001.jpg >> 640x512
Resized: ptfe-h2o-frame00000100.jpg >> 640x512
Resized: ptfe-h2o-frame00000200.jpg >> 640x512
Resized: ptfe-h2o-frame00000300.jpg >> 640x512
Resized: ptfe-h2o-frame00000400.jpg >> 640x512
Resized: ptfe-h2o-frame00000500.jpg >> 640x512

Pictures resized: 6
Time elapsed:      0:00:00.678194
pi@rpicam:/media/pi/data/PTFE/roi $ tree
.
├── ptfe-h2o-frame00000001.jpg
├── ptfe-h2o-frame00000100.jpg
├── ptfe-h2o-frame00000200.jpg
├── ptfe-h2o-frame00000300.jpg
├── ptfe-h2o-frame00000400.jpg
└── ptfe-h2o-frame00000500.jpg
    └── resize_x
        ├── ptfe-h2o-frame00000001.jpg
        ├── ptfe-h2o-frame00000100.jpg
        ├── ptfe-h2o-frame00000200.jpg
        ├── ptfe-h2o-frame00000300.jpg
        ├── ptfe-h2o-frame00000400.jpg
        └── ptfe-h2o-frame00000500.jpg


1 directory, 12 files
```

Version – 26.10.2020

```
pi@rpicam:/media/pi/data/PTFE/roi $ mediainfo resize_x/ptfe-h2o-
frame00000001.jpg
General
Complete name          : resize_x/ptfe-h2o-
frame00000001.jpg
Format                 : JPEG
File size              : 59.6 KiB

Image
Format                : JPEG
Width                 : 640 pixels
Height                : 512 pixels
Color space            : YUV
Chroma subsampling    : 4:2:0
Bit depth              : 8 bits
Compression mode       : Lossy
Stream size            : 59.6 KiB (100%)
```

The resized images are shown in the following sequence:



*Resized time-lapse images of a water droplet on PTFE.*

## 23 Convert Images to PNG Format

pics2png.py

- Convert image formats which PIL supports to PNG format
- Requires python PIL library
- RPI is not required

This simple program tries to read all files in current directory as PIL images. If it succeeds, then the image will be converted as a PNG file saved in a png named sub directory. The program does not require a RPI.

Here is an example run of the program:

```
$ pics2png.py
Pics to PNG files 1.0, (c) Kim Miikki 2019

20190322_102606.jpg (4032x2268) -> 20190322_102606.png
20190322_102611.jpg (4032x2268) -> 20190322_102611.png
20190322_102612.jpg (4032x2268) -> 20190322_102612.png
No PNG conversion: 20190322_102628.mp4

Pictures converted: 3
Time elapsed: 0:00:07.493193
```

## 24 Pictures to Time-lapse Files

gen\_tlfiles.py

- Copy and rename PNG or JPG files to time-lapse files
- RPI is not required

This application converts file names into time-lapse format (img\_0001, img\_0002 etc.). The files are copied and renamed. The program calculates a ratio of the nearest  $10^{\text{digits of pictures}}$ . If the amount of pictures is equal or more than 90 % to the following tenfold, the program will increase leading zeroes by one. New files are stored in a *tl* named directory under the the current directory.

Here is an example run of the program:

```
$ gen_tlfiles.py
Pictures to Time-lapse Files 1.0, (c) Kim Miikki 2020

cp /home/kim/pictemp/20190710_184746.jpg /home/kim/pictemp/tl/img_01.jpg
cp /home/kim/pictemp/20190710_184747.jpg /home/kim/pictemp/tl/img_02.jpg
cp /home/kim/pictemp/20190710_184749.jpg /home/kim/pictemp/tl/img_03.jpg
cp /home/kim/pictemp/20190710_184805.jpg /home/kim/pictemp/tl/img_04.jpg
cp /home/kim/pictemp/20190710_184808.jpg /home/kim/pictemp/tl/img_05.jpg
cp /home/kim/pictemp/20190710_184810.jpg /home/kim/pictemp/tl/img_06.jpg
```

Version – 26.10.2020

```
cp /home/kim/pictemp/20190710_184814.jpg /home/kim/pictemp/tl/img_07.jpg
cp /home/kim/pictemp/20190710_184815.jpg /home/kim/pictemp/tl/img_08.jpg
cp /home/kim/pictemp/20190710_184821.jpg /home/kim/pictemp/tl/img_09.jpg
cp /home/kim/pictemp/20190710_184825.jpg /home/kim/pictemp/tl/img_10.jpg
cp /home/kim/pictemp/20190710_184826.jpg /home/kim/pictemp/tl/img_11.jpg
cp /home/kim/pictemp/20190710_184827.jpg /home/kim/pictemp/tl/img_12.jpg
cp /home/kim/pictemp/20190710_184828.jpg /home/kim/pictemp/tl/img_13.jpg
cp /home/kim/pictemp/20190710_184830.jpg /home/kim/pictemp/tl/img_14.jpg
cp /home/kim/pictemp/20190710_184832.jpg /home/kim/pictemp/tl/img_15.jpg
cp /home/kim/pictemp/20190710_184833.jpg /home/kim/pictemp/tl/img_16.jpg
cp /home/kim/pictemp/20190710_184834.jpg /home/kim/pictemp/tl/img_17.jpg
cp /home/kim/pictemp/20190710_184835.jpg /home/kim/pictemp/tl/img_18.jpg
cp /home/kim/pictemp/20190710_185016.jpg /home/kim/pictemp/tl/img_19.jpg
cp /home/kim/pictemp/20190710_185020.jpg /home/kim/pictemp/tl/img_20.jpg
cp /home/kim/pictemp/20190710_185026.jpg /home/kim/pictemp/tl/img_21.jpg
cp /home/kim/pictemp/20190710_185105.jpg /home/kim/pictemp/tl/img_22.jpg
```

Time elapsed:0:00:00.072638

## 25 Additional Info

RPI High Speed Camera Suite, documentation and information for the RPI camera module:

<https://github.com/kmiikki/rpi-camera>, 20.10.2020

<https://www.raspberrypi.org/documentation/raspbian/applications/camera.md>, 27.12.2019

<https://picamera.readthedocs.io/en/release-1.13>, 2.1.2020